

Feed Program

All measurements are mL per 10L

MIXING ORDER	CLONE		VEGETATIVE				FLOWER									
	PRE SOAK	FEED	WEEK 1	WEEK 2	WEEK 3	WEEK 4	WEEK 1	WEEK 2	WEEK 3	WEEK 4	WEEK 5	WEEK 6	WEEK 7	WEEK 8	FLUSH	
1 st 2 nd 3 rd ANY ORDER ↓	Balance	Use as pH up		Use as pH up (Recommended for batch tank mixing and Dosatron. Do not use with NetaFlex)												
	Cleanse	3	3	5	5	5	5	5	5	5	5	5	5	5	5	26
	CaMg			5-8	5-8	5-8	5-8	5-8	5-8	5-8	5-8	5-8	5-8	5-8		
	Grow A			21	21	21	21									
	Grow B			21	21	21	21									
	Bloom A	13	26					29	29	32	32	26	24	10	8	
	Bloom B	13	26					29	29	32	32	26	24	10	8	
	PK									10	16	24	26	32	26	
TARGETS	EC	1.0	2.0	1.6	1.6	1.6	1.6	2.1	2.1	2.5	2.6	2.4	2.3	1.5	1.0	<0.1
	PPM 500	500	1000	800	800	800	800	1050	1050	1250	1300	1200	1150	750	500	<50
	PPM 700	700	1400	1120	1120	1120	1120	1470	1470	1750	1820	1680	1610	1050	700	<70
	pH	5.6		5.5-5.8 (Coco / Rockwool) 5.9-6.2 (Peat based mediums)				5.8-6.2 (Coco / Rockwool) 6.0-6.4 (Peat based mediums)				5.8-6.2 (Coco / Rockwool) 6.0-6.4 (Peat based mediums)				6.0-6.4 (All)

Spray Program

All measurements are mL per 10L

			VEGETATIVE				FLOWER		
APPLICATION FREQUENCY			WEEK 1	WEEK 2	WEEK 3	WEEK 4	WEEK 1	WEEK 2	WEEK 3
IPM	Preventative	2x week	158-238	158-238	158-238	158-238	60-90	158-238	158-238
	Pressure	3x week	238-317	238-317	90-120	238-317	238-317	238-317	238-317
Stack		2x week	18	18	18	18	18	18	18
Mix Together with IPM									

CLEANSE

Irrigation System Maintenance

Media/System Flush

Mix 25mL per 10L of water during the final flush to reduce mineral load in media and plant tissue.

Cuttings/Clones

25mL Cleanse per 10L of water. Dip fresh cuttings fully to improve cell health and increase immunity.

Foliar Application

Mix 100mL Cleanse per 1L of water and spray evenly. Test on a small area first to ensure no damage.

Surface Treatment/Cleaning

Mix 100mL Cleanse per 1L of water and spray all surfaces, tools, floors, and walls maintain a clean and trouble-free environment without toxic and dangerous chemicals.

STACK

Application Timing: Apply Stack from clone up to week 3 of flowering, or once plants stop growing vertically.

Foliar Application: 20mL per 10L of water and spray thoroughly twice weekly. Spray with lights off and allow to dry before turning on. Do not spray past week 3 of flower.

Seed Treatment: Mix 10mL per 10L of water and soak seed for 1-2 minutes before planting. Stack increases germination rates and plant vigor.

IPM

Before application:

- Shake well before mixing
- Turn off fans to ensure even coverage
- Turn off lights to reduce risk of damage
- Saturate growing media with water

During application:

- Wear appropriate protective gear (PPE)
- Drench the entire plant from stem to leaves